


EXHIBIT L

[Fleet 3 \(https://my.axon.com/s/axon-fleet3\)](https://my.axon.com/s/axon-fleet3) / Guide, Fleet

Technical information - Fleet 3

<https://my.axon.com/s/article/Technical-information-Fleet-3> Download PDF**ALPR permissions - Fleet 3** Last Modified - Jan 9, 2024

Fleet 3 results in Flock Safety search - Fleet 3

<https://my.axon.com/s/article/Fleet-3-results-in-Flock-Safety-search-Fleet-3>**ALPR permissions**

This topic is intended for Axon Evidence administrators. For user-based topics, start with [Introduction \(/s/article/Introduction-Fleet-3\)](/s/article/Introduction-Fleet-3).

Warranty and warnings - Fleet 3

<https://my.axon.com/s/article/Warranty-and-warnings-Fleet-3>

An admin must enable the appropriate permissions for the roles that will use ALPR before users can access and use ALPR functionality.

Enable permissions


Admin settings - Fleet 3

<https://my.axon.com/s/article/Admin-settings-Fleet-3>

1. On the menu bar in Axon Evidence, select **Admin**, then under Agency Settings select **Roles & Permissions**.

2. Do one of the following to either create or edit:

- Select **Create role**, then enter the role **Name** and select the license **Tier**. Or,


- Select **Edit**  on the line of the role you want to edit.

3. Scroll to the ALPR section and select **Allowed** or **Prohibited** as needed.

ALPR permissions - Fleet 3

<https://my.axon.com/s/article/ALPR-permissions-Fleet-3>

Cradlepoint configuration - Fleet 3

<https://my.axon.com/s/article/Cradlepoint-configuration-Fleet-3>

ALPR policy and public usage - Fleet 3

<https://my.axon.com/s/article/ALPR-policy-and-public-usage-Fleet-3>

- **Read/hit record search** – Lets a user search and view any agency ALPR records.
- **Hotlist management** – Lets a user search, modify, and create agency hotlists.
- **ALPR system administration** – Lets a user modify agency-level ALPR settings such as record retention and alert categories.


ALPR admin settings - Fleet 3

<https://my.axon.com/s/article/ALPR-admin-settings-Fleet-3>

The *Agency administrator* role has all three of these permissions by default. Admins can modify existing roles, create new roles, or copy and modify a role to enable Performance permissions.

Flock Safety integration - Fleet 3

<https://my.axon.com/s/article/Flock-Safety-integration-Fleet-3>

1. When done making changes, select **Save**  at the bottom. Axon Evidence begins enforcing the new permissions.

After you've created or edited your roles, don't forget to assign users to them.

Flock Safety search - Fleet 3

<https://my.axon.com/s/article/Flock-Safety-search-Fleet-3>**Next topic: [Cradlepoint configuration \(/s/article/Cradlepoint-configuration-Fleet-3\)](/s/article/Cradlepoint-configuration-Fleet-3)**

Upload evidence from Flock Safety - Fleet 3

<https://my.axon.com/s/article/Upload-evidence-from-Flock-Safety-Fleet-3>

Convert ALPR records to evidence - Fleet 3

<https://my.axon.com/s/article/Convert-ALPR-records-to-evidence-Fleet-3>